

Participant and User Maintenance Manual

Release 9.0

Version V1.0

Date 14 September 2020

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

© 2020 by Deutsche Börse AG ("DBAG"). All rights reserved.

All intellectual property, proprietary and other rights and interests in this publication and the subject matter of this publication are owned by DBAG, other entities of Deutsche Börse Group or used under license from their respective owner. This includes, but is not limited to, registered designs and copyrights as well as trademark and service mark rights. Methods and devices described in this publication may be subject to patents or patent applications by entities of Deutsche Börse Group.

Specifically, the following trademarks and service marks are owned by entities of Deutsche Börse Group: Buxl[®], DAX[®], DivDAX[®], eb.rexx[®], Eurex[®], Eurex Repo[®], Eurex Strategy WizardSM, Euro GC Pooling[®], F7[®], FDAX[®], FWB[®], GC Pooling[®], GCPI[®], M7[®], MDAX[®], N7[®], ODAX[®], SDAX[®], T7[®], TecDAX[®], USD GC Pooling[®], VDAX[®], VDAX-NEW[®] and Xetra[®].

The following trademarks and service marks are used under license and are property of their respective owners:

 \cdot All MSCI indexes are service marks and the exclusive property of MSCI Barra.

· ATX[®], ATX[®] five, CECE[®] and RDX[®] are registered trademarks of Vienna Stock Exchange AG.

· IPD[®] UK Annual All Property Index is a registered trademark of Investment Property Databank Ltd. IPD and has been licensed f or the use by Eurex for derivatives.

· SLI[®], SMI[®] and SMIM[®] are registered trademarks of SIX Swiss Exchange AG.

• The STOXX[®] indexes, the data included therein and the trademarks used in the index names are the intellectual property of STOXX Limited and/or its licensors Eurex derivatives based on the STOXX[®] indexes are in no way sponsored, endorsed, sold or promoted by STOXX and its licensors and neither STOXX nor its licensors shall have any liability with respect thereto.

· Bloomberg Commodity IndexSM and any related sub-indexes are service marks of Bloomberg L.P.

• PCS[®] and Property Claim Services[®] are registered trademarks of ISO Services, Inc.

· Korea Exchange, KRX, KOSPI and KOSPI 200 are registered trademarks of Korea Exchange Inc.

• BSE and SENSEX are trademarks/service marks of Bombay Stock Exchange ("BSE") and all rights accruing from the same, statutory or otherwise, wholly vest with BSE. Any violation of the above would constitute an offence under the law of India and international treaties governing the same.

Information contained in this publication may be erroneous and/or untimely. All descriptions, examples and calculations contained in this publication are for illustrative purposes only, and may be changed without further notice. Neither DBAG nor any entity of Deutsche Börse Group makes any express or implied representations or warranties regarding the information contained herein. This includes without limitation any implied warranty of the information's merchantability or fitness for any particular purpose and any warranty with respect to the accuracy, correctness, quality, completeness or timeliness of the information.

Neither DBAG nor any entity of Deutsche Börse Group shall be responsible or liable for any third party's use of any information contained in this publication under any circumstances. The information contained in this publication is not offered as and does not constitute investment advice, legal or tax advice, an offer or solicitation to sell or purchase any type of financial instrument.

Participant and User Maintenance Manual

Deutsche Börse Group

Version 1.0

Content	
1. Introduction	6
1.1 Purpose of this Manual	6
1.2 Maintenance Summary	7
1.3 Further Reading	7
1.4 What's new?	8
1.4.1 TES Compression	8
1.4.2 New role -> User Data View w/o PIN	9
1.4.3 Removal of Order Book Count Limits risk protection	9
2. Concepts	10
2.1 Product Assignment Groups	10
2.2 Participant Structure	10
2.3 Users	11
2.4 User Roles	11
2.5 Entitlement	13
2.6 Transaction Size Limits (Trading business unit only)	14
2.7 Maximum Order Value (Trading business unit only)	15
2.8 User Levels (Scope of Orders) (Trading business unit only)	15
2.8.1 On-exchange on-book trading	15
2.8.2 TES functionality	17
2.8.3 Eurex EnLight	18
3. Pre-defined User Roles	19
3.1 Service Administrator	20
3.1.1 Trading business unit	20
3.1.2 Clearing business units	21
3.2 User Data View	22
3.2.1 Trading business units	22
3.2.2 Clearing business units	23
3.3 User Data View w/o PIN	23
3.3.1 Trading business units	23
3.4 Trader	24
3.5 Market Maker	25
3.6 Trading View	26

T7 Derivatives Markets (EUREX)

T7 Derivatives Markets (EUREX)	Deutsche Börse Group
Participant and User Maintenance Manual	Version 1.0
3.7 TM Trade Overview	26
3.8 Emergency Trading Stop	27
3.9 Emergency Mass Deletion	28
3.10 Trade Enrichment Rule	29
3.11 Trade Enrichment Rule View	30
3.12 Pre-Trade Limits	31
3.13 Pre-Trade Limits View	32
3.14 Market Maker Protection	33
3.15 TES Trader	34
3.16 TES Broker	35
3.17 TES View	35
3.18 TES Compression	36
3.19 CM Pre-Trade Risk Maintenance	36
3.20 CM Pre-Trade Risk View	36
3.21 CM Backoffice View	36
3.22 Examination Trader Role	37
3.23 TES Examination Role	37
3.24 Stop Trading Participant Role / Stop Trading BU Role /	Stop Trading User Role 38
4. TES Type Eligibility	39
5. Maintenance	40
5.1 Product Assignment Groups & Transaction Size Limits	on business unit level 40
5.2 Users	40
5.2.1 Adding a user	41
5.2.2 Modifying a user	43
5.2.3 Password Rules	43
5.2.4 Deleting a user	43
5.3 Risk Controls	44
5.3.1 Stopping Trading for User	45
5.3.2 Stopping Trading for a Business Unit	46
5.3.3 Clearing Member Stopping a Trading Member	47
6. Appendix	48
6.1 Administrative roles	48
6.2 On-exchange on-book roles (only Trading business unit	ts) 49

T7 Derivatives Markets (EUREX)		Deutsche Börse Group	
Partici	pant and User Maintenance Manual	Version 1.0	
6.3	TES roles (only Trading business units)		51
6.4	Clearing business unit roles		51
6.5	Negative roles (only Trading business units)		52
7. CI	nange log		53

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

1. Introduction

T7 operates the on-exchange on-book (on-book) trading as well as the on-exchange off-book trading (off-book or also "TES T7 Entry Service") functionality of the Eurex derivatives exchange.

Using the Eurex Admin GUI, service administrators are able to add and maintain on-book and off-book users, including:

- Restricting access to products.
- Restricting functions.
- Restricting order and quote quantities.
- Restricting actions through user level, valid for
 - Scope of Orders
 - Scope of TES trades
 - Scope of Negotiation events
- Restricting which TES Types can be used.

For example, user functions and access to products can be restricted in T7 using the entitlement concept. Service administrators entitle users to specific roles for specific product assignment groups (e.g. a user may be entitled to a "Market Maker" role for the German Interest Rate Futures & Options).

New users are restricted from trading functions by default. This restriction can be only taken away by the exchange. Details are described in chapter 5.3.1

1.1 Purpose of this Manual

This manual is intended to assist service administrators who are responsible for maintaining participant and user related data in Eurex Exchange's T7.

The following areas are covered:

- Explanation of fundamental concepts.
- Pre-defined user roles (e.g. "Market Maker").
- Maintenance processes by service administrators.
- TES Type Eligibility

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

1.2 Maintenance Summary

Some data is maintained in the Eurex Clearing system (C7) and is automatically synchronized with Eurex Exchange's T7. The following is a summary of the data maintained in C7 and the data maintained in T7:

Data	Eurex Clearing System	Eurex Exchange's T7
Trading and Clearing members	\checkmark	
Participant / Business Unit		\checkmark
Product Assignment	\checkmark	
Transaction Size Limits (per member)		\checkmark
T7 Transaction Size Limits (per user)		\checkmark
T7 On-book Users and Off-Book Users		\checkmark
T7 User Groups		√
T7 User Roles		√
T7 Entitlements		√
T7 User Passwords		√
T7 Maximum Order Value		√
T7 Pre-Trade Risk		√
T7 TES Type Eligibility		√
T7 Auto-Approval rules		✓
T7 Eurex EnLight – SMART Respondent Assignment Anonymous Responder's Exclusion List		✓

Please refer to the document "Technical Connection Requests and Configuration – User Manual" for information on how to order and administer sessions (e.g. session id, password) for applications that access T7 via the electronic interfaces (Eurex ETI and Eurex FIX Gateway). The document is available in the member section of the Eurex website:

http://member.eurexchange.com > Help > Technical Connection > Manual Requests & Configuration

1.3 Further Reading

The following documents provide additional information to complement this manual:

- Eurex Functional and Interface Overview
- Eurex Trader and Admin GUI User Manual
- Eurex Functional Reference
- Eurex Functional / Technical Release Notes

These documents are available on the Eurex website <u>www.eurexchange.com</u> > Technology > T7 Trading Architecture > System Documentation.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

1.4 What's new?

This chapter shortly describes new/changed functionalities which have an impact on entitlement.

For detailed information about new functionalities, please refer to the "Functional/Technical Release Notes" and/or the "Functional Reference" document.

1.4.1 TES Compression

With T7 Release 9.0, Eurex will introduce the possibility for external compression service providers to offer exchange traded derivatives compression services for the Eurex market.

General Concept

Capital efficiency is and will remain an important topic for derivatives markets in the foreseeable future. The current and future regulation on capital requirements poses a continuous challenge to Eurex participants, impacting their trading activities at Eurex. Higher costs on derivatives positions is impacting and will impact traded volumes at Eurex. While it is expected that the upcoming regulation will ease the capital requirements, the focus for regulators is still on risk reduction.

Beside from simple close-out transactions, an important method to reduce the capital requirements resulting from derivatives positions is compression. Compression services are already established in the OTC market for other asset classes, especially for interest rate swaps.

Several compression service providers already offer their compression services in the OTC market. Eurex is aiming to set up a compression service infrastructure allowing external compression service providers to offer exchange traded derivatives compression services for the Eurex market.

External requirements for using the Compression Service at Eurex

The usage of the compression service at Eurex will be based on the following activities taking place outside the Eurex exchange environment:

• Creation of initial open positions:

Participants intending to use a compression service facilitated by Eurex will have a strong focus on reducing open positions. To join a compression run organized by a compression service provider, participants are required to accumulate open positions across different trading desks on product and instrument level resulting to one net initial open position per instrument.

- Interaction between compression service provider and trading participants: The trading participant is providing the initial open position to the compression service provider. The required interaction between a trading participant and a compression service provider will take place outside of the Eurex exchange environment.
- Creation of compression trades by external compression service provider: Based on the initial open position of the trading participants joining a compression run, the external compression service provider will create compression trades which may be regarded as a vehicle transforming the set of initial open positions into a set of compressed open positions by preserving selected key risk figures. The creation of compression trades will be performed outside the Eurex exchange environment.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

After these preconditions have been met, the compression service provider will be able to start the compression run in the exchange environment of Eurex.

- For the start and the release of the compression run by the Compression Service Provider, a dedicated role was created -> TES Compression Service
 - \circ $\;$ This role is only assigned to Trading Business Units upon request
- Upload and Approval of compression trades is part of the existing TES roles.

In addition, a new TES Type Eligibility is created -> Compression. This TES Type Eligibility is assigned to all Trading BUs with the introduction of release 9.0.

1.4.2 New role -> User Data View w/o PIN

With Release 8.1, Eurex introduced the concept of a mandatory PIN, used only for Trading-On-Behalf (ToB) activities, which is enforced by Eurex Market Supervision since 03.08.2020.

In addition, only Eurex users with the role "Service Administrator" or "User Data View" assigned can view the PIN of all users of the same Business Unit. The PINs are displayed in the User Maintenance screen of the Admin GUI.

Some members reported that due to their internal processes, not every user with "User Data View" role assigned should be able to see all PINs. They requested a similar role without a PIN view.

Therefore, Eurex decided to introduce the new role "User Data View w/o PIN". The role will be assigned to every Trading Business Unit, so that each service administrator can now assign this new role (and de-assign the original "User Data View") to those users, where a PIN view should not be displayed.

1.4.3 Removal of Order Book Count Limits risk protection

With T7 Release 9.0, the risk protection *Order Book Count Limits* will be removed which allowed a trading participant to restrict the number of orders and quotes per product, that a specific business unit or session may have in the order book at any time.

The risk protection *Order Book Count Limits* shall not be confused with the risk protection *Pre-Trade Risk Quantity Limits*. Participants are advised to apply the risk protection *Pre-Trade Risk Quantity Limits* instead of *Order Book Count Limits*.

The possibility to maintain and view these limits was included in the Pre-Trade Risk Roles. Therefore there is no action necessary with regards to entitlement.

Deutsche Börse Group

Participant and User Maintenance Manual


Version 1.0

2. Concepts

This chapter describes the fundamental concepts in Eurex Exchange's T7 regarding products, participants, users, entitlements and transaction size limits.

2.1 Product Assignment Groups

Each market in T7 includes a hierarchy of product assignment groups, containing products and instruments (options series / futures contracts). The product hierarchy is maintained by Eurex Exchange.



For example, the product assignment group "German Interest Rate Futures & Options" contains the products FGBL, FGBM, FGBS, FGBX, OGBL, OGBM, and OGBS. A simple instrument would be FGBL DEC 2015.

2.2 Participant Structure

There is one participant for every trading and clearing member, according to the following structure:



Participant data is set up and maintained by Eurex Exchange, and a participant is authorized to a market (e.g. Eurex). The Eurex concept of a member remains in place and is represented by a "participant" in T7. When trades are sent to the Eurex Clearing system, the participant is represented by its corresponding member-ID.

Currently in T7, a participant has up to two pre-defined business units. Trading members have one business unit designated for trading, under which all trading users are assigned.

Clearing members have one business unit designated for clearing. Clearing business units can receive all on-book and off-book trades from every trading member for whom they are the designated clearing member.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

A Clearing business unit can have users. These users are set up for the maintenance/view of other users or for the maintenance/view of the parameter settings for the "Pre-Trade Risk" functionality. Initially each Clearing business unit will get one user set up by the exchange. This user acts as Service Administrator and is able to set up and maintain all other users for this Clearing business unit.

Clearing members that also trade, will have both a Trading and a Clearing business unit. There is no interaction between the two types of business units (e.g. a user acting as Service Administrator of a Trading business unit cannot view, set up or maintain users from the related Clearing business unit and vice versa).

Every business unit has a business unit short name (e.g. clearing business unit "ABCFRCL"), as well as a unique numeric business unit ID.

2.3 Users

A user is a person, such as a trader or a service administrator that interacts with Eurex Exchange's T7. A user may also be a machine, for example an order routing or quoting system.

Every user of T7 belongs to exactly one Trading business unit or Clearing business unit.

Service administrators define a user short name with 6 digits (e.g. TRD001).

A unique numeric user ID is automatically generated for each user and is used by T7's electronic interfaces.

A user login name is also generated, combining the participant ID (e.g. "ABCFR") with the user short name, for use in the Eurex Trader and Eurex Admin GUIs.

Service Administrators can assign PINs to users. Users can view their own PIN in the login window of the Trader GUI and Admin GUI.

2.4 User Roles

Participants can restrict functions that users are allowed to perform, and for which products they are entitled. Eurex Exchange's T7 includes a set of pre-defined user roles, configured and maintained by Eurex Exchange. User roles offer participants a simplified approach to administration:

- Sets of resources (e.g. mass quote) are combined to define a logical user role (e.g. "Market Maker").
- A participant assigns roles to users, and multiple roles can be assigned to the same user (multiple user IDs are not needed).
- A user is granted entitlements for specific roles for specific product assignment groups (see 2.5)
- Resources that are not allowed for a specific user role (e.g. mass quote by trader role) are restricted using a negative entitlement concept, explained below.

Refer to section 3 for the complete set of pre-defined user roles available to participants.

The negative entitlement concept prevents a user from being granted certain resources in the case when they have been assigned to more than one user role in the same product assignment group. For example, as shown in the following diagram, negative entitlement is configured for mass quote and quote activation for the trader role – this means, that even if the user is assigned another role where

T7 Derivatives Mar	kets (EUREX)
--------------------	--------------

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

mass quote is allowed (e.g. "Market Maker"), the negative entitlement will block that function, and mass quoting will still be prevented. Negative entitlement does not apply when a user is assigned to a different role in a different product assignment group.

Negative entitlement is not used for Clearing business units.

The following diagram is an example of the user role concept, showing that a subset of all available resources (on the left) is selected to form a role (trader role on the right):

Resources available	-	Trader role resouces	
Add Order		Add Order	
Modify Order		Modify Order	
Delete Order		Delete Order	
Delete all orders		Delete all orders	_
Mass Quote		Mass Quote	Negative
Delete All Quotes		Quote (De)Activation	Entitlements
Quote (De)Activation		Add Complex Instrument	
Modify Market Maker Protection		Cross Request	
Add Complex Instrument		Quote Request	
Cross Request			
Quote Request			

Deutsche Börse Group

Participant and User Maintenance Manual


Version 1.0

2.5 Entitlement

Participants entitle users for specific user roles for specific product assignment groups.

For example, user TRD001 has a supervisor user level and has been entitled to a trader role for product assignment group 1 and emergency trading stop and user data view roles for the entire market. User TRA056 has been entitled to a trading view role in product assignment group 1 and a market maker role in product assignment group 2.

Participants can assign users to more than one role, however certain restrictions apply that are described further in sections 2.4 and 3.



The following diagram shows some example combinations of entitlements:

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

2.6 Transaction Size Limits (Trading business unit only)

Participants can restrict order and quote quantities using transaction size limits (maximum order quantities).

The possibility to trade products within a PAG is controlled by the TSL setting. These TSL will no longer be set by the Clearing member for their Trading Participants in Eurex Classic, but by the Eurex Exchange (on levels On-Exchange on-book, TES and Calendar Spread) per product. Trading members' assignment of TSLs to their users is not affected

C7 sends a "Product Assignment" to T7. Each clearing member can define which related Trading Participant is allowed to trade which product. This information is taken as trigger for the assignment of TSL on business unit level in T7:

- If the trading business unit has a product assignment, then T7 calculates the member TSL based on the above-mentioned levels on product level.
- If the trading business unit has no product assignment, then T7 will remove the TSL.

Example

ABCFR as GCM gives its Trading Participant DEFFR the assignment for product "ABCD". Eurex has set the TSL levels for "ABCD" to 999.999 for On-Exchange on-book Trading, 99.999 for TES and 9.999.999 for spreads.


As a result, the trading participant DEFFR will get the above-mentioned TSL assigned.

Transaction size limits for a specific user and product are maintained by participants themselves, using the Eurex Admin GUI, and the following values can be configured:

- Maximum order quantity
- Maximum calendar spread quantity
- Maximum TES quantity

T7 Derivatives Markets (EUREX)	Deutsche Börse Group
Particinant and User Maintenance Manual	Version 1.0

If the values entered exceed the limits established for the trading business unit, the lower limits will apply:



Default transaction size limits can be configured for a user and product assignment group, and will be inherited for all new products added to the group.

2.7 Maximum Order Value (Trading business unit only)

Participants can set maximum order value limits for their users. The trading system calculates the value of each order entered into the order book and compares it to the maximum order value defined on user level. If the order value exceeds the defined maximum order value, then the order is rejected. It is possible to skip this validation for orders and quotes entered via ETI or FIX gateways. Orders entered via the T7 GUI will always be validated against the maximum order value limits.

MaxOrderValue is only valid for the on-exchange order book (on-book) trading. The on-exchange offbook trading (off-book or also "TES T7 Entry Service") functionality does not validate against this value.

Detailed information and the formulas for order value calculation will be provided in the T7 Functional Reference document.

Note that the functionality described above applies also for quotes.

2.8 User Levels (Scope of Orders) (Trading business unit only)

2.8.1 On-exchange on-book trading

Every user is designated to have one (and only one) user level: trader, head trader or supervisor. Users enter their own orders, and their user level defines which orders they are authorized to act upon (scope of orders):

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

User Level	Scope of Orders
1 – Trader	Modify and delete own orders only.
2 – Head Trader	Modify and delete own orders, as well as orders entered by other users in the same user group.
3 – Supervisor	Modify and delete own orders, as well as orders entered by other users in the entire business unit.

An order entered into Eurex Exchange's T7 belongs to the entering user. If a second user changes this order, ownership of this order will transfer to the second user. Only exchange Market Supervision can enter an order on behalf of another user.


When using the new Eurex Trader GUI, the user level affects which orders and trades a user is able to view. For example, a trader can view only their trades, whereas a head trader can view all trades within the user group.

Quotes are entered using Eurex ETI sessions. The context to modify or delete quotes is defined by the session used. For orders, the entering session also defines what orders can be viewed, modified and deleted by others (e.g. modification by another session of the same business unit is only supported for standard orders). For further information, please refer to the document "Eurex Enhanced Trading Interface – Manual".

Participants define the user structure themselves, to reflect their business operations and practices. One or more supervisors can be defined, who are entitled to perform actions for the entire trading business unit.

One or more user groups can optionally be defined. More than one head trader can be set up in a user group, and a supervisor may or may not be assigned to a user group. Users can belong to one user group only.

The following diagram shows an example of user levels contained within user groups, contained within a trading business unit:



Please note that users can only act upon orders in product assignment groups for which they are entitled, regardless of their user level (entitlement overrides user level), see 2.5.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

2.8.2 TES functionality

The behavior for TES is slightly different to the one for on-exchange on-book trading.

A <u>user level</u> is a mandatory user attribute which determines a user's right to perform TES maintenance actions for other users from the same business unit or from the same user group:

User Level	Scope of (TES) Trades		
1 – Trader	Delete and approve own TES trades only.		
2 – Head Trader	A user with a user level of Head Trader may delete TES Trades of ar Initiating user belonging to the same user group and approve TES sides of any Approving Trader belonging to the same user group.		
3 – Supervisor	A user with a user level of Supervisor may delete TES Trades of any Initiating user belonging to the same business unit and approve TES sides of any Approving Trader belonging to the same business unit.		

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

2.8.3 Eurex EnLight

The behavior for Eurex EnLight is slightly different to the one for on-exchange on-book trading.

A user level is a mandatory user attribute which determines a user's right to perform Eurex EnLight maintenance actions for other users from the same business unit or from the same user group:

User Level	Scope of Negotiation Event
1 – Trader	The trader may update the Negotiation Event, enter orders in Eurex EnLight and cancel deals for his user ID. The trader may enter/ update/ delete quotes to the service and approve or reject deals in Eurex EnLight for his user ID.
2 – Head Trader	The head trader of a user group may update the Negotiation Event, enter orders in Eurex EnLight and cancel deals on-behalf of the requester belonging to the same user group. The head trader may enter/ update/ delete quotes to the service and approve or reject deals in Eurex EnLight on-behalf of the respondent belonging to the same user group.
3 – Supervisor	A supervisor of a business unit may update the Negotiation Event, enter orders in Eurex EnLight and cancel deals on-behalf of the requester belonging to the same business unit. The supervisor can also enter/ update/ delete quotes to the service and approve or reject deals in Eurex EnLight on-behalf of the respondent belonging to the same business unit.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3. Pre-defined User Roles

This chapter describes the pre-defined user roles available to participants in Eurex Exchange's T7 (information in brackets indicate if the role can be used by Trading or Clearing business units):

- Service Administrator (Trading / Clearing)
- User Data View (Trading / Clearing)
- User Data View w/o PIN (Trading)
- Trader (Trading)
- Market Maker (Trading)
- Trading View (Trading)
- TM Trade Overview (Trading)
- Emergency Trading Stop (Trading)
- Emergency Mass Deletion (Trading)
- Trade Enrichment Rule (Trading)
- Trade Enrichment Rule View (Trading)
- Pre-trade Limits (Trading)
- Pre-trade Limits View (Trading)
- CM Pre-Trade Risk Maintenance (Clearing)
- CM Pre-Trade Risk View (Clearing)
- CM Backoffice View (Clearing)
- Market Maker Protection (Trading)
- TES Trader (Trading)
- TES Broker (Trading)
- TES View (Trading)
- TES Compression Service (Trading)
- Examination Trader Role (special "negative" role, prevents the user from trading and can only be de-assigned by the exchange. Further details in chapter 3.22) (Trading)
- TES Examination Role (special "negative" role, prevents the user from TES trading and can only be de-assigned by the exchange. Further details in chapter 3.23) (Trading)
- Stop Trading BU (special "negative" role, prevents the user from trading. Is assigned and deassigned automatically if BU is stopped by the member or the exchange or the user is stopped by the member. Further details in chapter 3.24) (Trading)
- Stop Trading User (special "negative" role, prevents the user from trading. Is assigned and deassigned automatically if user is stopped by the exchange. Further details in chapter 3.24) (Trading)
- Stop Trading Participant (special "negative" role, prevents the user from trading. Is assigned and de-assigned automatically if participant is stopped. Further details in chapter 3.24) (Trading)

A summary of user roles and resource assignments can be found in the appendix (see 6).

A Trading business unit user is granted entitlements for specific roles for specific product assignment groups. Some roles are only applied market wide (in T7 GUI referred as on-exchange attributes).

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

Product Assignment Group	Service Admin.	User Data View	User Data View w/o PIN	Trade Enrichment Rule / View	Pre- Trade Limits / View	TM Trade Overview	
Market Wide	√	√	√	√	√	√	
Product Assignment Group	Emergency Trading Stop	Emergency Mass Delete	TES Compression Service				
Market Wide	√	√	√				

A Clearing business unit user is granted entitlements for specific roles, which are only applied market wide

Product Assignment Group	Service Admin.	User Data View		CM Pre-Trade Risk Maintenance	CM Pre-Trade Risk View
Market Wide	~	√	√	V	\checkmark

The following are examples of role assignments for on-book trading and TES functionality (TES includes the usage of Eurex EnLight functionality):

Product Assignment Group	Trader	Market Maker	Market Maker Protection	Trading View	TES Trader	TES Broker	TES View
ENSOEE	√						V
SNSOEC	√				~	~	
BFFHIE		√	√				
XNCOQE		√	√				
XACFQU				✓			

3.1 Service Administrator

3.1.1 Trading business unit

Participants appoint one or more service administrators to create and maintain all types of users. This includes resetting passwords, assigning entitlements, setting transaction size limits (including default transaction size limits) as well as maximum order value. Please note that new trading users must be activated by the exchange. Service Administrators can also maintain PINs for the users.

The following table shows the specific resources assigned to the Service Administrator role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users incl. PIN	\checkmark	TES Approve	
View Users	√	TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	√
Maintain Trade Enrichment Rules		TES Type Eligibility View	√
Add Flexible Instrument		Eurex EnLight - Maintenance of Disclosure Parameters	\checkmark
CLIP Trading		T7 Auto-Approval rules	√
T7 Eurex EnLight – SMART Respondent Assignment	√	T7 Eurex EnLight – Anonymous Responder's Exclusion List	V

A service administrator user may also be assigned additional roles.

In order to assign the emergency trading stop role to a service administrator, the user level must be set to supervisor. The service administrator role is assigned to an entire market, not a product assignment group.

The service administrator role enables the viewing of all users and entitlements (it is not required to also entitle the user data view).

For new participants, Eurex Exchange generates the first service administrator user. This user cannot be modified by the member to prevent accidental deletion of the sole administrator.

3.1.2 Clearing business units

Participants appoint one or more service administrators to create and maintain all types of users. This includes resetting passwords, assigning entitlements.

The following table shows the specific resources assigned to the Service Administrator role:

Resource	Role	Resource	Role
Maintain Users	√	Maintain Pre-Trade Risk Limits	
View Users	√	View Pre-Trade Risk Limits	

A service administrator user may also be assigned additional roles.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

The service administrator role enables the viewing of all users and entitlements (it is not required to also entitle the user data view).

For new participants, Eurex Exchange generates the first service administrator user.

3.2 User Data View

3.2.1 Trading business units

A user data view role is available to enable a user to view all users, entitlements, transaction size limits and maximum order value, without update capability. The user data view role is assigned to an entire market, not a product assignment group.

The following table shows the specific resources assigned to the User Data View role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users	✓	TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	\checkmark
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	√
CLIP Trading		View PIN	√

23

T7 Derivatives Markets (EUREX)

Participant and User Maintenance Manual

Clearing business units 3.2.2

A user data view role is available to enable a user to view all users, entitlements, but without update capability. The user data view role is assigned to an entire market, not a product assignment group.

The following table shows the specific resources assigned to the User Data View role:

Resource	Role	Resource	Role
Maintain Users		Maintain Pre-Trade Risk Limits	
View Users	\checkmark	View Pre-Trade Risk Limits	

3.3 User Data View w/o PIN

Trading business units 3.3.1

A user data view role is available to enable a user to view all users, entitlements, transaction size limits and maximum order value, without update capability and without the ability to view the user PINs. The user data view role is assigned to an entire market, not a product assignment group.

The role is available only to Trading Business Units.

The following table shows the specific resources assigned to the User Data View role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users	√	TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	√
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	√
CLIP Trading		View PIN	

Version 1.0

Deutsche Börse Group

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.4 Trader

The trader role enables order handling functions, cross requests, quote requests, and adding of complex instruments.

Mass quoting and quote (de)activation is not allowed for a trader role, and therefore defined with negative entitlement, see 2.4.

The trader role is assigned to specific product assignment groups.

The following table shows the specific resources assigned to the Trader role:

Resource	Role	Resource	Role
Add order	\checkmark	View Trade Enrichment Rules	
Modify Order	V	Maintain Pre-Trade Limits	
Delete Order	\checkmark	View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)	√	Stop trading for Business Unit	
Mass Quote	Neg. Entitlement	Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)	Neg. Entitlement	Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument	√	TES Entry	
Cross Request	\checkmark	TES Modify	
Quote Request	√	TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading	√		

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.5 Market Maker

The market maker role enables all quoting and order handling functions, cross requests, and adding of complex instruments. Quote request is not allowed for a market maker role and is therefore defined with negative entitlement.

<u>A user must not be assigned both a trader role and a market maker role for the same product</u> <u>assignment group.</u> Doing so will result in a conflict of negative entitlements, and block the mass quote, quote (de)activation and quote request functions entirely for that user for the product assignment group.

The market maker role is assigned to specific product assignment groups.

The market maker role does not include the modification of market maker protection parameters. This resource was taken out and added to the new role "Market Maker Protection" (chapter 3.12). As a result, members are able to separate market making from the maintenance of these parameters.

The following table shows the specific resources assigned to the Market Maker role:

Resource	Role	Resource	Role
Add order	√	View Trade Enrichment Rules	
Modify Order	√	Maintain Pre-Trade Limits	
Delete Order	√	View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)	√	Stop trading for Business Unit	
Mass Quote	√	Release trading for Business Unit	
Delete All Quotes	\checkmark	Stop Trading for User	
Quote De(Activation)	√	Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument	√	TES Entry	
Cross Request	\checkmark	TES Modify	
Quote Request	Neg. Entitlement	TES Broker	
Inquire Market Maker Parameter	\checkmark	TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading	√		

Note that the mass quote resource includes all functions to enter and modify single and multiple quotes.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.6 Trading View

The trading view role only applies to users of the Eurex Trader GUI and provides restricted display access to trading data in the Market View, Order View, Trade View Time & Sales View and Ticker View windows. The trading view role is assigned to specific product assignment groups and is not required if a user is already assigned a trader or market marker role.

The Eurex Trader GUI displays market information only for products that the user is assigned a trading view, trader or market maker role for the corresponding product assignment group.

3.7 TM Trade Overview

The TM Trade Overview role only applies to users of the Eurex Trader GUI and provides restricted display access to trading data in the Market View, Trade View Time & Sales View and Ticker View windows. The trading view role is assigned to the whole market and is not required if a user is already assigned a trader or market marker or a trading view role.

Difference to the role "Trading View" -> User is not enabled to see orders and the role is not assigned to a PAG, but to the whole market.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.8 Emergency Trading Stop

The emergency trading stop role enables risk control functions to stop trading for a user or the entire business unit, and automatically delete orders and quotes (deletion of quotes only in case of stop trading BU).

In addition, the following TES trades will be deleted if the business unit / user is stopped -> All TES trades where a stopped user is involved and where the TES trade is not yet finally approved. That includes TES trades where the stopped user has already approved the TES trade, but any other counterpart has not done this yet.

In case a business unit is stopped, this applies to all users of the business unit.

The emergency trading stop role can be added to supplement any other role, as long as the user level is set to supervisor. The emergency trading stop role is assigned to an entire market, not a product assignment group.

Participants must have at least two users with the emergency trading stop role in order to stop a user or business unit from trading; stop trading functions use the four-eyes principle as a safeguard, see 5.3.

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	√
Mass Quote		Release trading for Business Unit	√
Delete All Quotes		Stop Trading for User	\checkmark
Quote De(Activation)		Release Trading for User	√
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading	✓	TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

The following table shows the specific resources assigned to the Emergency Trading Stop role:

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.9 Emergency Mass Deletion

The emergency mass deletion role enables the market wide deletion of all orders and quotes for all products via the Eurex Trader GUI or the Eurex Admin GUI. This functionality has no impact on TES trades. It only applies to on-exchange on-book trading.

Deletion of orders can be performed for a specific user or for the entire business unit. The scope of orders allowed to be selected for deletion is controlled by the assigned user level, see 2.8. For example, trader level can mass delete own orders only, and supervisor level can mass delete all orders for an entire business unit.

The user level is not relevant for mass deletion of quotes. With this role assigned, any user level can delete all quotes for the entire business unit.

The emergency mass deletion role can be added to supplement any other role, and is assigned to an entire market, not a product assignment group.

The following table shows the specific resources assigned to the Emergency Mass Deletion role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	√
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.10 Trade Enrichment Rule

A trade enrichment rule role is available to enable a user to view and maintain trade enrichment rules for the entire business unit, using the Eurex Admin GUI. Trade enrichment rules are a feature of Eurex Exchange's T7, and are used for automatic enrichment of executed quotes, and executed orders that use the short order message layout. The trade enrichment rule role is assigned to an entire market, not a product assignment group.

This functionality has no impact on TES trades. It only applies to on-exchange on-book trading.

The trade enrichment rule role can be added to supplement any other role. Without this role, individual users are unable to view or maintain trade enrichment rules.

For information about trade enrichment rules functionality, please refer to the document "Eurex Functional Reference".

The following table shows the specific resources assigned to the Trade Enrichment Rule role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	√
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules	\checkmark	TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.11 Trade Enrichment Rule View

A trade enrichment rule view role is available to enable a user to view all trade enrichment rules without update capability. The trade enrichment rule view role is assigned to an entire market, not a product assignment group.

This functionality has no impact on TES trades. It only applies to on-exchange on-book trading.

The following table shows the specific resources assigned to the Trade Enrichment Rule view role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	√
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.12 Pre-Trade Limits

A pre-trade limits role is available to enable a user to view and maintain pre-trade limits for the entire business unit, using the Eurex Admin GUI. Pre-trade limits are a feature of Eurex Exchange's T7 that enable participants to set functional limits on the number of open orders and quote sides stored in an order book.

This functionality has no impact on TES trades. It only applies to on-exchange on-book trading.

The pre-trade limits role can be added to supplement any other role. Without this role, individual users are unable to view or maintain pre-trade limits.

For information about pre-trade limits functionality, please refer to the document "Eurex Functional Reference".

The following table shows the specific resources assigned to the Pre-Trade Limits role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	√
Delete Order		View Pre-Trade Limits	√
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.13 Pre-Trade Limits View

A pre-trade limits view role is available to enable a user to view all pre-trade limits without update capability. The pre-trade limits view role is assigned to an entire market, not a product assignment group.

This functionality has no impact on TES trades. It only applies to on-exchange on-book trading.

The following table shows the specific resources assigned to the Pre-Trade Limits View role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	√
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.14 Market Maker Protection

A user with this role is able to maintain market maker protection parameters and to delete quotes.

This role was implemented to enable members to separate the trading (market maker role) from the risk control (market maker protection role).

The following table shows the specific resources assigned to the Market Maker Protection role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes	√	Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection	✓	Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	
Inquire Market Maker Parameter	✓	TES Delete	
Maintain Users		TES Approve	
View Users		TES View	
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument		Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.15 TES Trader

The TES Trader role enables the entry, modification, deletion and the approval of TES trades.

This role is used, if the entering user is directly participating in a TES trade, where the TES Broker role is used where the user is not a part of the TES trade. A user can have both roles assigned.

The TES Trader role is assigned to specific product assignment groups.

In addition: If a TES Trader role is assigned to a user within a business unit, then the user can act as requester and respondent in the Eurex EnLight functionality (user is allowed to enter RFQ, update RFQ, enter quote, update quote, create deal, approve or reject deal).

With Release 8.0, Eurex has introduced Straight Through Processing (STP) for Eurex EnLight. In case of STP, all requesters and all responders must have TES TRADER role assigned.

The following table shows the specific resources assigned to the TES Trader role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument	\checkmark	TES Entry	√
Cross Request		TES Modify	\checkmark
Quote Request		TES Broker	
Inquire Market Maker Parameter		TES Delete	\checkmark
Maintain Users		TES Approve	√
View Users		TES View	√
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument	√	Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.16 TES Broker

The TES Broker role enables the entry (as a broker), modification and deletion of TES trades.

This role is used if the entering user is NOT directly participating in the TES trade, where the TES Trader role is used where the user is part of the TES trade. A user can have both roles assigned.

The TES Broker role is assigned to specific product assignment groups.

In addition: If a TES Broker role is assigned to a user within a business unit, then the user can act as requester and respondent in the Eurex EnLight functionality (user is allowed to enter RFQ, update RFQ, enter quote, update quote, create deal, approve or reject deal).

With Release 8.0, Eurex has introduced Straight Through Processing (STP) for Eurex EnLight.

The following table shows the specific resources assigned to the TES Broker role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete All Orders (Product/Instrument level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument	\checkmark	TES Entry	
Cross Request		TES Modify	\checkmark
Quote Request		TES Broker	\checkmark
Inquire Market Maker Parameter		TES Delete	\checkmark
Maintain Users		TES Approve	
View Users		TES View	\checkmark
Delete All for STOP Trading		TES Type Eligibility Maintenance	
Maintain Trade Enrichment Rules		TES Type Eligibility View	
Add Flexible Instrument	√	Eurex EnLight – Viewing of Disclosure Parameters	
CLIP Trading			

3.17 TES View

The TES view role only applies to users of the Eurex Trader GUI and provides restricted display access to TES trading data in the TES View window. The TES view role is assigned to specific product assignment groups and is not required if a user is already assigned a TES trader or TES Broker role.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

3.18 TES Compression

The TES Compression role is assigned to TES Compression Service Providers only. The assignment of the role needs to be requested explicitly.

The role includes the ability to start and release compression runs.

3.19 CM Pre-Trade Risk Maintenance

A CM Pre-Trade Risk Maintenance role is available to enable a user to maintain and view all Risk Control parameters set for all Trading business units related to the Clearer. The CM Pre-Trade Risk Maintenance role is assigned to an entire market, not a product assignment group.

The following table shows the specific resources assigned to the User Data View role:

Resource	Role	Resource	Role
Maintain Users		Maintain Pre-Trade Risk Limits	✓
View Users		View Pre-Trade Risk Limits	√
View Trades of related Trading Participants			

3.20 CM Pre-Trade Risk View

A CM Pre-Trade Risk View role is available to enable a user to view all Risk Control parameters set for all Trading business units related to the Clearer, but without update capability. The CM Pre-Trade Risk View role is assigned to an entire market, not a product assignment group.

The following table shows the specific resources assigned to the User Data View role:

Resource	Role	Resource	Role
Maintain Users		Maintain Pre-Trade Risk Limits	
View Users		View Pre-Trade Risk Limits	√
View Trades of related Trading Participants			

3.21 CM Backoffice View

A CM Backoffice View role is available to enable a user to look at trades from their related Trading Participants on the Clearing GUI. The CM Backoffice View role is assigned to an entire market, not a product assignment group.

Resource	Role	Resource	Role
Maintain Users		Maintain Pre-Trade Risk Limits	
View Users		View Pre-Trade Risk Limits	
View Trades of related Trading Participants	√		

Participant and User Maintenance Manual

Version 1.0

3.22 Examination Trader Role

The Examination Trader role prevents a user of a trading member from trading activities. It is automatically assigned to each new user and will be de-assigned by the exchange if the user has a trader exam and is therefore allowed for trading.

The following table shows the specific resources assigned to the Examination Trader role:

Resource	Role	Resource	Role
Add Order Neg. Entitlement		Maintain Users	
Modify Order	Neg. Entitlement	View Users	
Delete Order	Neg. Entitlement	CM Trade View	
Delete All Orders (Product/Instrument level)	Neg. Entitlement	Maintain Trade Enrichment Rules	
Mass Quote	Neg. Entitlement	View Trade Enrichment Rules	
Delete All Quotes	Neg. Entitlement	Stop trading BU by CM	
Quote De(Activation)	Neg. Entitlement	Release trading BU by CM	
Cross Request	Neg. Entitlement	Stop Trading for User	
Quote Request	Neg. Entitlement	Release Trading for User	
Add Short Order	Neg. Entitlement	Modify Short Order	Neg. Entitlement
CLIP Trading Neg. Entitlement			

3.23 TES Examination Role

The TES Examination role prevents a user of a trading member from TES trading activities. It is automatically assigned to each new user and will be de-assigned by the exchange if the user has a trader exam and is therefore allowed for trading.

The following table shows the specific resources assigned to the TES Examination role:

Resource	Role	Resource	Role
Add order		View Trade Enrichment Rules	
Modify Order		Maintain Pre-Trade Limits	
Delete Order		View Pre-Trade Limits	
Delete all Orders (Product/Instrument Level)		Stop trading for Business Unit	
Mass Quote		Release trading for Business Unit	
Delete All Quotes		Stop Trading for User	
Quote De(Activation)		Release Trading for User	
Modify Market Maker Protection		Delete All Orders / Quotes for All Products	
Add Complex Instrument		TES Entry	
Cross Request		TES Modify	
Quote Request		TES Broker	

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

Inquire Market Maker Parameter	TES Delete
Maintain Users	TES Approve Neg. Entitlement
View Users	TES View
Delete All for STOP Trading	TES Type Eligibility Maintenance
Maintain Trade Enrichment Rules	TES Type Eligibility View
Add Flexible Instrument	CLIP Trading

3.24 Stop Trading Participant Role / Stop Trading BU Role / Stop Trading User Role

These roles prevent a user of a trading member from trading activities. They are automatically assigned to each user in case the participant or the BU or the user is stopped. As soon as the participant or the BU or the user stop is released, the roles will automatically be de-assigned.

The following table shows the specific resources assigned to these roles:

Resource	Role	Resource	Role
Add Order	Neg. Entitlement	Maintain Users	
Modify Order	Neg. Entitlement	View Users	
Delete Order	Neg. Entitlement	CM Trade View	
Delete All Orders (Product/Instrument level)	Neg. Entitlement	Maintain Trade Enrichment Rules	
Mass Quote	Neg. Entitlement	View Trade Enrichment Rules	
Delete All Quotes	Neg. Entitlement	Stop trading BU by CM	
Quote De(Activation)	Neg. Entitlement	Release trading BU by CM	
Cross Request	Neg. Entitlement	Stop Trading for User	
Quote Request	Neg. Entitlement	Release Trading for User	
Add Short Order Neg. Entitlement		Modify Short Order	Neg. Entitlement
TES Entry Neg. Entitlement		TES Approve	Neg. Entitlement
TES Modify Neg. Entitlement		TES Delete	Neg. Entitlement
TES Broker Neg. Entitlement		CLIP	Neg. Entitlement

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

4. TES Type Eligibility

The TES Type Eligibility on T7 is used to control access to the various TES Types

- Block Trade (includes FLEX and Trade at Market (TAM))
- Exchange for Physicals (EFP) Fin
- Exchange for Physicals (EFP) Index
- Exchange for Swaps (EFS)
- Vola Trade
- EnLight
- BLOCK_QTPIP
- Compression

Flex Contracts are included in TES Type "Block Trade".

TES Type Eligibility is set on participant level and on user level.

The participant level assignment is done by the Eurex Exchange. Every participant is enabled to use all available TES Types.

The service administrator can then assign the TES Type Eligibility to the user. This is done in the Admin GUI, using the User Maintenance screen.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

5. Maintenance

This chapter describes the maintenance functions that will be performed by service administrators.

Data related to product assignment groups, participants, business units, users and risk controls will be made available to service administrators, including all identifiers needed for all interfaces.

5.1 Product Assignment Groups & Transaction Size Limits on business unit level

Product assignment groups are created and maintained by Eurex Exchange T7.

With release 8.0, there was a change in PAG logic. All trading business units in T7 will automatically get all PAGs assigned. The possibility to trade the products within the PAG is now controlled by the TSL setting. These TSL will no longer be set by the Clearing member in Eurex Classic, but by the Eurex Exchange (on levels On-exchange on-book, TES and Spread) per product.

C7 sends a "Product Assignment" to T7. Each clearing member can define which related Trading Participant is allowed to trade which product. This information is taken as trigger for the assignment of TSL on business unit level in T7:

- If the trading business unit has a product assignment, then T7 calculates the member TSL based on the above-mentioned levels on product level.
- If the trading business unit has no product assignment, then T7 will set the member TSL to "NULL".

Example:

ABCFR as GCM gives its Trading Participant DEFFR the assignment for product "ABCD". Eurex has set the TSL levels for "ABCD" to 999.999 for On-Exchange Trading, 99.999 for TES and 9.999.999 for spreads.

As a result, DEFFR will get the above mentioned TSL assigned.

5.2 Users

This section describes the steps necessary to maintain users of Eurex Exchange's T7.

Authorization can be configured by service administrators, as follows (T / C indicates if relevant for Trading or Clearing business unit):

Participant and User Maintenance Manual

Version 1.0

Type of restriction	Achieved by		
Restrict products (T)	Product assignment groups, see 2.1 (also transaction size limits for product level)		
Restrict functions (T / C)	User roles (e.g. market maker or trading view), see 2.4		
Restrict quantities traded (T)	Transaction size limits, see 2.6		
Restrict value traded (T)	Maximum Order Value limit, see 2.7		
Restrict scope of orders (T)	User levels (trader, head trader, supervisor), see 2.8		
Restrict scope of TES Types (T)	TES Type Eligibility, see chapter 4		

Viewing restrictions apply to users of the Eurex Trader GUI; these restrictions may not be implemented in alternative applications that access T7 via the electronic interfaces.

5.2.1 Adding a user

Service administrators are able to add users themselves, according to the following steps:

#	Task	Description
1	Apply for Trader Admission	Participants must apply for admission for all on-book trading users (trader role or market maker role) and all users who should be allowed to approve TES trades.
		This is done using the eXAS (Electronic Exchange Admission Service) tool available in the Eurex member section.
		This step can be skipped if the user is a non-trading on-exchange user or a user not allowed to approve TES trades or a simulation user.
2	Apply for user	This is mandatory for all trading users and TES users and strongly recommended for non-trading users. This is done using the eXAS tool available in the Eurex member section.
		This step is not applicable to simulation users.

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

#	Task	Description		
3	Create user in Eurex Exchange's T7	Using the Eurex Admin GUI, a User Setup Wizard will guide service administrators through the necessary steps, to add:		
		 User attributes (e.g. name, user level, user group, etc.) Entitlements (roles per product assignment groups) Transaction size limits MaxOrderValue TES Type Eligibility PIN Initial password, either entered manually, or automatically generated (for password rules, see 5.2.3) Trading users and TES users must be activated by Eurex Exchange before they can trade using T7.		
		A unique numeric user ID will be generated for each user and is available for display and export on the Eurex Admin GUI, as well as on reports RD110, RD115, RD120 and RD125 available in the Common Report Engine. These numeric identifiers are used in all of the electronic interfaces to T7 (Eurex ETI and Eurex FIX Gateway).		
4	Activate user (done by exchange)	Prior to activation, new trading users will be assigned a negative entitlement "Trader Examination Role" that will prevent on-book trading activity as well as a negative entitlement "TES Examination Role" that will prevent TES approval activities (all other TES activities are still possible; e.g. TES Entry, TES Modify etc.).		
		Eurex Exchange will activate on-book trading users and users allowed to approve off-book TES trades when the admission process and all above steps are completed.		
		Eurex Exchange will activate TES users not allowed for approval of TES trades the day after the user application is completed in eXAS and the user is set up as TES user in T7.		
		Simulation users are activated upon request, by emailing clearingdata@eurexchange.com.		
		Non-trading users can immediately begin using T7 after the user is created (step #3 above).		

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

5.2.2 Modifying a user

Using the Eurex Admin GUI, service administrators may modify user information. If a non-trading user is updated to become a trading user, there must be a trader admission, see 5.2.1, step #1. The same applies to users who are updated to allow TES Approval.

Modifications to the user attributes (transaction size limits, entitlement, TES Type Eligibility, user group, user level and password resets) are effective immediately. Users must log out and then log back in for these changes to take effect.

5.2.3 Password Rules

User password requirements for Eurex Exchange's T7 are:

- minimum of 8 and a maximum of 16 characters
- valid characters: [a-z, A-Z, 0-9] and special characters: ['+', '-', '@', '!', '_', '\$', '%', '&', '/', '=', '*','#']
- minimum 1 uppercase letter and minimum 1 lowercase letter
- minimum 1 special character
- maximum number of repeated characters allowed is 6
- a password history is maintained to prevent the last 10 passwords from being re-used.

User passwords do not automatically expire. Users are able to change their passwords themselves. Passwords can only be changed using the GUI.

Passwords generated during setup of new users and passwords generated during password reset by Service Administrator will automatically expire after first login. The user is then forced to create a new password.

Participants are responsible for the regular refresh of user passwords, according to their own security guidelines.

5.2.4 Deleting a user

Service administrators may delete users, according to the following steps:

#	Task	Description
1	Notify Exchange	Eurex Exchange should be notified of all user deletions. This is required for all on-book and off-book trading users and non- trading users, using the eXAS tool. This step is not applicable for simulation users.
2	Delete user	User deletions are done using the Eurex Admin GUI and are effective for the next day (but user login is prevented immediately).

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

Before deleting a user, participants should ensure that there are no open orders or TES trades or Eurex EnLight Negotiation Events remaining in the system that were entered by this user. Any open orders, TES trades or Negotiation Events for Eurex EnLight for deleted users are automatically removed at the end of the trading day (relevant for users of Trading business unit).

Participants are responsible for immediate deletion of a user account, when the associated person is no longer with the organization.

5.3 Risk Controls

Risk control functions are available in Eurex Exchange's T7 for participants to stop a user or an entire business unit from trading.

Clearing members may stop one of their trading members in the Eurex Clearing system, which is automatically synchronized with T7.

Stopped users can continue to view trading activity, but are not able to enter new orders or quotes.

Please take into account that stopping and releasing a BU/User require two users (4Eyes Principle), both with emergency trading stop role, to execute the function. In case the second user does not approve the transaction, it will not be deleted during the nightly end-of-day run. It remains in the same status (waiting for approval).

Remark: Risk Controls mentioned in this chapter are not related to the functionality "Pre-Trade Risk Control".

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

5.3.1 Stopping Trading for User

Users entitled to the emergency trading stop role may stop and release any user as follows:

#	Task	Description
1	Stop Trading for user	When a user is stopped (and confirmed), using the Admin GUI, any orders belonging to the user are immediately deleted.
		Note that quotes will not be deleted – quotes belong to the entering session, not a specific user.
		In addition, the following TES trades will be deleted if the business unit / user is stopped -> All TES trades where a stopped user is involved and where the TES trade is not yet finally approved. That includes TES trades where the stopped user has already approved the TES trade, but any other counterpart has not done this.
		If a stopped user is subsequently released, the user may resume trading activities. Previously deleted orders are not restored.
		Negotiation Events are not affected by the stop of a user. But as soon as the resulting transaction of this event will be entered as TES trade, it will be rejected.
2	Confirm Stop / Release (four-eyes principle)	The stop and release functions require that two users, both with emergency trading stop role, execute the function. If a stopped user is subsequently released, the user may resume
		trading activities. Previously deleted orders are not restored.

Participant and User Maintenance Manual

Version 1.0

5.3.2 Stopping Trading for a Business Unit

Users entitled to the emergency trading stop role may stop and release an entire business unit as follows:

#	Task	Description
1	Stop Trading for business unit	When a business unit is stopped (and confirmed), using the Admin GUI, all orders and quotes within the business unit are deleted.
		In addition, the following TES trades will be deleted if the business unit / user is stopped -> All TES trades where a stopped user is involved and where the TES trade is not yet finally approved. That includes TES trades where the stopped user has already approved the TES trade, but any other counterpart has not done this.
		Negotiation Events are not affected by the stop of a business unit. But as soon as the resulting transaction of this event will be entered as TES trade, it will be rejected.
2	Confirm Stop / Release (four-eyes principle)	The stop and release functions require that two users, both with Emergency Trading Stop role, execute the function. If the stopped business unit is subsequently released, all users may resume trading activities, except for any users previously stopped individually. Previously deleted orders and quotes are not restored.

Participant and User Maintenance Manual

Version 1.0

5.3.3 Clearing Member Stopping a Trading Member

Using the Eurex Clearing system, a clearing member may stop a trading member, for whom they are a designated clearing member, as follows:

#	Task	Description
1	Stop Trading Member	This is done using the Eurex C7 ARP.
		When a trading member is stopped, the corresponding trading business unit in T7 is automatically stopped, and all orders and quotes within the business unit are deleted.
		In addition, the following TES trades will be deleted if the business unit / user is stopped -> All TES trades where a stopped user is involved and where the TES trade is not yet finally approved. That includes TES trades where the stopped user has already approved the TES trade, but any other counterpart has not done this.
		Negotiation Events are not affected by the stop of a business unit. But as soon as the resulting transaction of this event will be entered as TES trade, it will be rejected.
		If the stopped business unit is subsequently released in the Eurex Clearing system, all users may resume trading activities. Previously deleted orders and quotes are not restored.

Eurex Frankfurt AG

Eurex Participant and User Maintenance Manual

V5.0.001

6. Appendix

The following tables show the specific resources assigned to the various roles, separated by context.

6.1 Administrative roles

Resource / Role	Service Admin. (T/C)	User Data View (T/C)	User Data View w/o PIN (T)	Emergency Trading Stop (T)
Modify Market Maker Protection				
Add Complex Instrument				
Cross Request				
Quote Request				
Inquire Market Maker Parameter				
Maintain Users	√			
View Users	√	√	√	
Delete All for STOP Trading				\checkmark
PIN View	√	√		
Maintain Trade Enrichment Rules				
View Trade Enrichment Rules				
Maintain Pre-Trade Limits				
View Pre-Trade Limits				
Stop Trading for BU				√
Release Trading for BU				√
Stop Trading for User				√
Release Trading for User				√
Delete all Orders/Quotes for all Products				
TES Entry				
TES Modify				
TES Broker				
TES Delete				
TES Approve				
TES View				
TES Type Eligibility Maintenance	√			
TES Type Eligibility View	√	√	√	
Eurex EnLight - Maintenance of Disclosure	✓			
Eurex EnLight - Viewing of Disclosure Parameters	√	√	√	
T7 Auto-Approval rules	√			
T7 Eurex EnLight – SMART Respondent Assignment	V			
T7 Eurex EnLight – Anonymous Responder's Exclusion List	V			
				Only Supervisor Level

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

6.2 On-exchange on-book roles (only Trading business units)

Resource / Role	Trader	Market Maker	Trading View	TM Trade Overview	Emergency Mass Delete
Add Order	√	√			
Modify Order	√	√			
Delete Order	√	√			
Delete All Orders (Product/Instrument level)	√	~			
Mass Quote	Neg. Ent	√			
Delete all Quotes		√			
Quote De(Activation)	Neg. Ent	√			
Modify Market Maker Protection					
Add Complex Instrument	√	√			
Cross Request	√	√			
Quote Request	√	Neg. Ent			
Inquire Market Maker Parameter		V			
Maintain Users					
View Users					
Delete All for STOP Trading					
Maintain Trade Enrichment Rules					
View Trade Enrichment Rules					
Maintain Pre-Trade Limits					
View Pre-Trade Limits					
Stop Trading for BU					
Release Trading for BU					
View Orders			V		
View Trades			√	V	
Delete all Orders/Quotes for all Products					V
CLIP Trading	~	~			
			Trader GUI only	Trader GUI only	

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

Resource / Role	Trade Enrichment Rule	Trade Enrichment View	Pre-Trade Limits	Pre-Trade Limits View	Market Maker Protection
Add Order					
Modify Order					
Delete Order					
Delete All Orders (Product/Instrument level)					
Mass Quote					
Delete all Quotes					√
Quote De(Activation)					
Modify Market Maker Protection					V
Add Complex Instrument					
Cross Request					
Quote Request					
Inquire Market Maker Parameter					~
Maintain Users					
View Users					
Delete All for STOP Trading					
Maintain Trade Enrichment Rules	√				
View Trade Enrichment Rules	√	√			
Maintain Pre-Trade Limits			~		
View Pre-Trade Limits			~	V	
Stop Trading for BU					
Release Trading for BU					
View Orders					
View Trades					
Delete all Orders/Quotes for all Products					
CLIP Trading					

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

6.3 TES roles (only Trading business units)

Resource / Role	TES Trader.	TES Broker	TES View	TES Compression Service
TES Entry	√			
TES Modify	√	√		
TES Broker		√		
TES Delete	√	√		
TES Approve	√			
TES View	√	~	√	
TES Type Eligibility Maintenance				
TES Type Eligibility View				
Add Complex Instrument	√	~		
Add Flexible Instrument	\checkmark	√		
Start / Release TES Compression run				V

6.4 Clearing business unit roles

Resource / Role	Service Administrator	User Data View	CM Pre-Trade Risk Maintenance	CM Pre- Trade Risk View	CM Backoffice View
Maintain users	√				
View users	√	√			
Maintain Pre-Trade Risk parameters			✓		
View Pre-Trade Risk parameters			\checkmark	√	
View Trades of related Trading Participants					~

Deutsche Börse Group

Participant and User Maintenance Manual

Version 1.0

6.5 Negative roles (only Trading business units)

Resource / Role	Examination Trader Role	TES Examination Role	Stop Trading Participant Stop Trading BU Stop Trading User
Add Order	Neg. Entitlement		Neg. Entitlement
Modify Order	Neg. Entitlement		Neg. Entitlement
Delete Order	Neg. Entitlement		
Delete All Orders (Product/Instrument level)	Neg. Entitlement		
Mass Quote	Neg. Entitlement		Neg. Entitlement
Delete all Quotes	Neg. Entitlement		
Quote De(Activation)	Neg. Entitlement		Neg. Entitlement
Cross Request	Neg. Entitlement		Neg. Entitlement
Quote Request	Neg. Entitlement		Neg. Entitlement
Maintain Users			
CLIP Trading	Neg. Entitlement		Neg. Entitlement
View Users			
Delete All for STOP Trading			
Maintain Trade Enrichment Rules			
View Trade Enrichment Rules			
Stop Trading for BU			
Release Trading for BU			
Stop Trading for User			
Release Trading for User			
Delete all Orders/Quotes for all Products			
Add Short Order	Neg. Entitlement		Neg. Entitlement
Modify Short Order	Neg. Entitlement		Neg. Entitlement
TES Approval		Neg. Entitlement	Neg. Entitlement

Participant and User Maintenance Manual

Version 1.0

7. Change log

No	Chapter, page	Date	Change
9.0.001	General	14/09/2020	Initial Version for Release 9.0